

# New in April 2025

---

## Updated performance & consumption tasks

We're rolling out new features and improved user interfaces across the Performance and Consumption tasks in Easy PV. These updates will help you generate system performance and consumption projections more accurately than ever.

We've summarised the key changes below, but we also recommend reading the full user guides to understand how to use the new versions of these tasks and the new features we've added: [Performance task user guide](#) and [Consumption task user guide](#).

## Improved user interfaces

We've been working on improvements to many of the user interfaces in Easy PV to make them more intuitive and efficient. These UI upgrades are designed to make it quicker and easier to complete tasks and take full advantage of the new and existing features.

## Automatic panel stringing

We've introduced automatic panel stringing, which recommends a suitable way to string panels based on the roofs and inverter inputs in your design. This new feature is a real time-saver—especially for larger systems—by helping you set up strings quickly and efficiently. You can manage preferences on your account to set how you want automatic panel stringing to apply. See below for more information.


### Performance ⓘ

- Location
- Roofs
- Panel allocation**
- Self consumption

### Panel Allocation ⓘ

We have auto-selected the allocation of panels to inverter inputs.


#### Roof 1



Fox ESS KH 10kW 1ph Hybrid

Input 1   Input 2   Input 3

#### Roof 2




Fox ESS KH 10kW 1ph Hybrid

Input 4

## New domestic and commercial consumption profiles

You can now choose from a variety of domestic and commercial consumption profiles to build an accurate picture of energy usage throughout the year. A consumption profile calculates when energy is consumed—both annually and on a daily basis. For example, in a domestic home, most energy is typically used in the early morning and evenings. In contrast, an office profile reflects higher energy use during typical working hours, from around 09:00 to 17:00.


**The following commercial profiles are available**



## Configure export limits and visualise export and inverter clipping

We've added support for setting export limits where required by the DNO. This ensures your system design complies with local network requirements and accurately reflects any restrictions on energy export and the potential financial benefits of the system.

You can toggle on clipping in the consumption task to show relevant information in the charts. This makes it easier to visualise when and how much potential generation is being limited by the inverter or by export limits, helping you make more informed design choices and assess whether an inverter is appropriately sized for the system.



## Configure Performance task preferences

You can now set preferences on your account for how you want the Performance task to work.

**Mode:** Choose between **MCS** and **NREL** methods to calculate the total annual generation

**Panel allocation:** Set whether you want Easy PV to:

- **automatically allocate panels** - this will entirely skip this step in the performance task if panels can be allocated automatically (you can return to this if you later want to change the allocation).
- **Suggest allocation** - this will display the suggested allocation which you can accept or edit.
- **Manual allocate panels** - this will ignore suggested panel allocation and you will need to allocate panels manually.

**MCS Self Consumption:** Choose whether you want to:

- **use default values for MCS self consumption** - this will let you set default values which will be used by default for each of the inputs required for the MCS consumption calculations.
- **manually enter MCS self consumption** - if you select this option you will need to set the inputs required for the MCS calculations on every project.

**Sunpaths:** Choose whether you want Easy PV to automatically calculate shading based on the terrain and 3D buildings or whether you want this to be excluded so you can set the shading manually.

## Performance Settings

These will be used as the settings for the performance task.

Mode

MCS



Panel Allocation

Suggest Allocation



MCS Self Consumption

Manually enter MCS self...




Sunpaths

Automatically calculate shadin...



## Set default roof margins

You can now set a default roof margin to apply to all your projects. This is a margin around the edges of a roof that panel arrays should not overlap. It is shown as a yellow line on the roofs in the Easy PV Panels Task. If you use the auto-fill functionality to add panels automatically to the roof, it will ensure no panels cover the roof margin.



## For standard (free) Easy PV accounts

Navigate to your **account preferences** then select the **design** tab. Enter the roof margin in millimetres (mm) that you want to be applied by default to your new projects. You can override this on a per-project basis via the panels task.

# User Preferences

General   Connect To Midsummer   Financial   **Design**   Performance

## Design Settings

These will be used as the base settings when creating a new project. They can be overridden on a per-project basis.

### Design defaults

Roof margin

400

mm

Enter the default roof margin in mm that you want to be applied to all roofs. Easy PV can auto-fill roofs with panels and will ensure panels avoid the margins you set, and any other obstructions added to the roof.

## For PRO Easy PV accounts

Navigate to your **PRO account settings** and select the **design** tab. Enter the roof margin in millimetres (mm) that you want to be applied by default to new projects for all your users. This will override any defaults the users have set on their own account preferences, but they will be able to override the default margin on a per-project basis via the panels task.

# Team Preferences

General   Financial   Documents   Customer Proposal   Email   **Design**   CRM Connections   Speedy PV *Beta*

## Design Settings

These will be used as the base settings when creating a new project. They can be overridden on a per-project basis.

### Design defaults

Roof margin

600

mm

Enter the default roof margin in mm that you want to be applied to all roofs. Easy PV can auto-fill roofs with panels and will ensure panels avoid the margins you set, and any other obstructions added to the roof.

Revision #10

Created 26 September 2024 12:11:19 by Matt Agnes

Updated 29 April 2026 08:38:29 by Matt Agnes